


HTML5 SOLO MINING (Windows 7)


1. Download HTML5Coin wallet.
2. Open it, sync to 100%.
(May take a while depending on your connection and the size of the blockchain)
3. Close wallet completely.
(Make sure no processes of the wallet are in your task manager)
4. Press Start, then type in %APPDATA%, and hit enter, your \Roaming\ folder will show up, scroll down and navigate to your HTML5 folder, and open it.
(You can also navigate to C:\Users\YOURUSERNAME\AppData\Roaming\HTML5)
5. You will need to make a HTMLcoin.conf with notepad.

I use this:

```
server=1
listen=1
daemon=1
rpcuser=username
rpcpassword=password
rpccallowip=127.0.0.1
rpcport=3333
```




Name	Modified	Type	Size
database	11/2/2014 7:19 PM	File folder	
txleveldb	11/2/2014 8:22 PM	File folder	
.lock	10/20/2014 2:49 A...	LOCK File	0 KB
blk0001.dat	11/2/2014 8:23 PM	DAT File	45,239 KB
db	10/20/2014 2:49 A...	Text Document	0 KB
debug	11/2/2014 8:24 PM	Text Document	2,093 KB
Htmlcoin	10/20/2014 3:29 A...	CONF File	1 KB
peers.dat	11/2/2014 8:24 PM	DAT File	67 KB
wallet.dat	11/2/2014 8:23 PM	DAT File	168 KB



6. Set your .conf as needed, save and close it.
7. Next you will have to launch the wallet with -server command. You can do this via CMD or by creating a shortcut and adding -server to the end of the Target text field. Open



8. Once that opens up, you can then start mining via 127.0.0.1:3333 -u user -p password



```
C:\Windows\system32\cmd.exe
sgminer v4.2.1 - Started: [2014-11-02 20:38:52] - [0 days 00:05:27]
(Ss) 1.517M (avg) 211.7Kh/s | R:0 R:0 HM:0 WU:0.000/m
ST: 2 SS: 0 NB: 8 LM: 0 GF: 0 RF: 0
Connected to 127.0.0.1 (longpoll) diff 1.357 as user user
Block: 1563bb91... Diff:1 Started: [20:43:33] Best share: 0
[P]ool management [G]PU management [S]ettings [D]isplay options [Q]uit
GPU 0: 54.0C 100% | 1.398M/211.7Kh/s | R: 0.0% HM:0 WU:0.000/m I:17
```

HTML5COIN Donations Welcome: HSWYq1ovPbyzdEKPF3qKgwdB8Jb7rwwFFd Thank You :-)